

Auto Account Setup

Connect to other server types.

 **E-mail Account**

Your Name:

Example: Ellen Adams

E-mail Address:

Example: ellen@contoso.com

Password:

Retype Password:

Type the password your Internet service provider has given you.

 Text Messaging (SMS) **Manually configure server settings or additional server types**

< Back

Next >

Cancel

Choose Service

 **E-mail Account**

Connect to an e-mail account provided by your Internet service provider (ISP) or your organization.

 Text Messaging (SMS)

Connect to a mobile messaging service.

 Other

Connect to a server type shown below.

Fax Mail Transport

< Back

Next >

Cancel

Choose Service

 **Internet E-mail**

Connect to POP or IMAP server to send and receive e-mail messages.

 Microsoft Exchange or compatible service

Connect and access e-mail messages, calendar, contacts, faxes and voice mail messages.

 Text Messaging (SMS)

Connect to a mobile messaging service.

 Other

Connect to a server type shown below.

Fax Mail Transport

< Back

Next >

Cancel

Internet E-mail Settings

Each of these settings are required to get your e-mail account working.

**User Information**

Your Name:

E-mail Address:

Server Information

Account Type:

Incoming mail server:

Outgoing mail server (SMTP):

Logon Information

User Name:

Password:

Remember password

Require logon using Secure Password Authentication (SPA)

Test Account Settings

After filling out the information on this screen, we recommend you test your account by clicking the button below. (Requires network connection)

Test Account Settings by clicking the Next button

Once the fields to the left are complete, click More Settings...

< Back

Next >

Cancel

Internet E-mail Settings



General

Sent Items

Deleted Items

Outgoing Server

Connection

Advanced

My outgoing server (SMTP) requires authentication

Use same settings as my incoming mail server

Log on using

User Name:

Password:

Remember password

Require Secure Password Authentication (SPA)

OK

Cancel

Internet E-mail Settings



General

Sent Items

Deleted Items

Outgoing Server

Connection

Advanced

Server Port Numbers

Incoming server (IMAP):

143

Use Defaults

Use the following type of encrypted connection:

TLS

Outgoing server (SMTP):

587

Use the following type of encrypted connection:

TLS

Server Timeouts

Short



Long 1 minute

Folders

Root folder path:

Incoming port must be: 143

Outgoing port must be: 587

Incoming encryption type must be: TLS

Outgoing encryption type must be: TLS

OK

Cancel